



Installation Manual

NTT ADVANCED TECHNOLOGY CORPORATION

Trademarks

The names described below and other names of companies and products in this document are trademarks or registered trademarks of their respective companies. The TM, ®, and © marks are omitted in this document.

- WinActor is a registered trademark of NTT ADVANCED TECHNOLOGY CORPORATION.
- Microsoft, Windows^{*1}, Internet Explorer and Excel are trademarks or registered trademarks of Microsoft Corporation in the United States and other countries.

^{*1} The official name of Windows is Microsoft Windows Operating System.

- The names of other companies and products are trademarks or registered trademarks of their respective companies.

About this document

This "WinActor Installation Manual" (hereinafter referred to as "this manual") describes the steps before using WinActor.

- ① Purchasing a license from an agency
- ② Obtaining a WinActor installer from the agency
- ③ Installing WinActor
- ④ Launching WinActor

If you use the evaluation edition of WinActor, the following steps are not necessary.

There are three ways to register the license: "Online license registration," "License registration via WinActor license issuance site," and "License registration via agency." Use one of these three ways to register the license.

1. Online license registration
 - ⑤ Registering the license online on WinActor
2. License registration via WinActor license issuance site
 - ⑤ Applying a license issuance on the WinActor license issuance site
 - ⑥ Downloading the issued license on the WinActor license issuance site
 - ⑦ Registering the license
3. License registration via agency
 - ⑤ Sending a product ID file to the agency
 - ⑥ Obtaining a license file from the agency
 - ⑦ Registering the license

Window images and texts used in this manual may vary depending on the OS and settings.

- Notes on this manual
- The copyright notice "Copyright © 2013-2026 NTT, Inc. & NTT ADVANCED TECHNOLOGY CORPORATION" attached to this manual and the provided software cannot be changed or deleted.
The copyright of this manual belongs to NTT, Inc. and NTT ADVANCED TECHNOLOGY CORPORATION.
- The descriptions in this manual assume that users understand Windows operations and functions. For information that is not described in this manual, see the documents provided by Microsoft.

- Symbols in this manual

The symbols used in this manual have the following meanings.

	Particularly important information
	Supplementary information for texts, window descriptions, operations, etc.
	Reference information to other pages of this manual or other manuals

Contents

Trademarks.....	i
About this document.....	ii
Contents.....	v
1. Installing WinActor	1
1.1 Installer without manual	3
1.1.1 Installation method for administrator.....	3
1.1.2 Installation method for standard user.....	13
1.2 Installer with manual	21
1.3 Association of scenario files.....	22
1.4 Disassociation of scenario files.....	22
1.5 Virtual keyboard driver for canceling the screen saver.....	24
1.5.1 Install the driver.....	24
1.5.2 Uninstall the driver.....	27
1.6 Manual installer	30
1.6.1 Installing manuals.....	30
2. Launching WinActor	35
2.1 Launching WinActor	35
2.2 Checking the license type	38
2.2.1 Display differences among license types.....	38
2.2.2 Displaying the About WinActor dialog.....	42
2.2.3 Displaying the Option dialog	43
3. [NL] License registration	44
3.1 Online license registration.....	45
3.2 License registration via WinActor license issuance site	50
3.2.1 License issuance and renewal.....	51
3.3 License registration via agency.....	60
3.3.1 License issuance request.....	60
3.3.2 Obtaining a license file	63
3.3.3 License registration steps	64
3.4 Steps for registering a license by copying from Ver.5 or Ver.6	69
4. [NL] License transfer	73


4.1 Online license transfer	74
4.2 License transfer via WinActor license issuance site	79
4.3 License transfer via agency	93
5. [FL] Setting the license server connection information.....	99
6. [AL] AI integration license server connection settings	105
7. Setting the management server connection information	110
8. Checking the server connection status	115

1. Installing WinActor

This chapter describes how to install WinActor.



- If you are already using WinActor Ver.5 or Ver.6, specify a folder **different from WinActor Ver.5 or Ver.6** as a folder to install WinActor Ver.7.
The default folder name is "WinActor" for WinActor Ver.5 or Ver.6, and "WinActor7" for WinActor Ver.7.
- If you are already using WinActor Ver.7 and want to update it to a newer version of WinActor Ver.7, the update procedure is the same as the installation procedure.
Follow the installation instructions in this chapter to update.
- Carry out the installation with WinActor closed.
When WinActor is launched, its icon will be stored in the task tray at the lower right of the Windows screen. You can close WinActor by right-clicking the icon and selecting 'Quit.'




- If the extension function of WinActor is installed in a browser, stop running the browser while updating WinActor.
 - There are two types of WinActor installers. Use the installer without manual when installing WinActor on an environment with Internet connectivity, or the installer with manual when installing WinActor on an environment without Internet connectivity.
 - If multiple users use WinActor on one Windows 11 computer, install WinActor for administrator.
-



- WABAgent is not necessary for WinActor Ver.7.3.0 and its successors.
Before installing or updating WinActor, quit WABAgent and delete the startup shortcut of it following the procedure described below.


Open the task tray, which is called overflow area, at the right bottom of the Windows screen clicking the 'Show hidden icons' arrow on the task bar.

When the icon of WABAgent exists, right-click the icon and select 'Quit.' When the icon does not exist, just proceed to the next step.



Then, enter "shell:startup" into the address bar of the Windows explorer to display the startup folder.

When the shortcut "Automatically start WABAgent" exists in the startup folder, delete the shortcut. When the shortcut does not exist, skip this step.



1.1 Installer without manual

This section describes the installation of WinActor with the installer without manual.

When WinActor is installed with the installer without manual, manuals are downloaded on access via Internet and displayed. It is recommended to install WinActor with the installer without manual when Internet connectivity is available.

If Internet connectivity is unavailable, install WinActor with the installer with manual. About the installer with manual, refer “1.2 Installer with manual.”


If you already have installed WinActor Ver.7, you can update it with the same procedure.

1.1.1 Installation method for administrator

Using the installer without manual, WinActor is being installed for all the users in this section.


Steps

1. Start the installer "WinActorSetup.exe" in the "WinActor_Installer" folder.




WinActor setup program will be launched.

2. When the 'Select Setup Language' dialog appears, select English and click the 'OK' button.




The selection dialog of WinActor installation modes is displayed.

3. Confirm that the 'WinActor for administrator' is selected, click the 'Next' button.



The 'User Account Control' dialog is displayed.


4. Click the 'OK' button.



The License Agreement dialog will be shown.


If WinActor Ver.7 is already installed, a confirmation dialog to overwrite the existing WinActor will be displayed.

Click the 'Yes' button to update to a new version of WinActor Ver.7. In that case, Step 5 (specifying a folder to install WinActor) will be skipped.



Click the 'No' button to cancel the installation.

5. Read through the entire end user license agreement, check "I accept the agreement" and then click the 'Next' button.




A step to specify a location to install WinActor will be displayed.



In the title bar of the installer, the version number of the WinActor is displayed.

6. Specify a folder to install WinActor and click the 'Next' button.

The initial folder name is "WinActor7."



The selection dialog of license types will be displayed.

When overwriting the preexisting WinActor installed with the installation mode, which is either 'for administrator' or 'for standard user,' different from the mode selected at step 3, the installation of WinActor may display the dialog of the message *The install mode, which is either ...*

When you install the WinActor for administrator over the WinActor for standard user, set another folder for the new installation.

When you have selected the wrong installation mode, close the installer and retry installation from the beginning.




Do not install WinActor Ver.7 to the folder of WinActor Ver.5 or Ver.6.



For information on the handover of node-locked license of WinActor Ver.5 or Ver.6, see "3.4 Steps for registering a license by copying from Ver.5 or Ver.6."

7. Select the license type to apply using the radio buttons and click the 'Next' button.



 For license types, see "2.2 Checking the license type."

The dialog to specify the start menu folder will be shown.

When overwriting the preexisting WinActor installed with the license type different from the type selected at this step, the installation of WinActor may display the dialog of the message *The destination of WinActor and License Type ...*


When you install the WinActor of another license type, set another folder for the new installation.

When you have selected the wrong license type, close the installer and retry installation from the beginning.

8. Enter a Start Menu folder and click the 'Next' button.




If you do not want to create a Start Menu folder, check "Don't create a Start Menu folder."



A dialog to select additional tasks will be displayed.

9. Select whether to create a desktop shortcut, whether to install the driver to cancel the screen saver, and whether to install Google Chrome or Firefox browser agent. After that, click the 'Next' button.




A step to confirm the installation details will be displayed.



When the Google Chrome or the Firefox browser agent is installed, operations on the corresponding browser can be recorded and replayed on WinActor.

Browser agents can be installed via WinActor after the installation of WinActor. For the installation procedure, see “WinActor Chrome Agent Installation Manual” and “WinActor Firefox Agent Installation Manual.”


10. Check the details and click the 'Install' button.



The installation progress will be displayed.




It may take about 10 minutes to complete the installation.



When the installation is completed, the following completion dialog appears.

11. Click the 'Finish' button.




1.1.2 Installation method for standard user

Using the installer without manual, WinActor is being installed for the current user only in this section.


Steps

1. Start the installer "WinActorSetup.exe" in the "WinActor_Installer" folder.




WinActor setup program will start.

2. When the 'Select Setup Language' dialog appears, select English and click the 'OK' button.




The selection dialog of WinActor installation modes is displayed.

3. Confirm that the 'WinActor for standard user' is selected, click the 'Next' button.



The dialog of the 'License Agreement' is displayed.

4. Read the entire end user license agreement, check "I accept the agreement" and then click the 'Next' button.



A step to specify a location to install WinActor will be displayed.



In the title bar of the installer, the version number of the WinActor is displayed.


5. Specify a folder to install WinActor and click the 'Next' button.

The initial folder name is "WinActor7."

However, the WinActor folder of the last launched WinActor for standard user will be displayed as default when WinActor has already been installed.



Specify a folder to which a standard user has write permission (such as Desktop for example).



The selection dialog of license types will be displayed.

When overwriting the preexisting WinActor installed with the installation mode, which is either 'for administrator' or 'for standard user,' different from the mode selected at step 3, the installation of WinActor may display the dialog of the message *The install mode, which is either ...*

When you install the WinActor for standard user over the WinActor for administrator, set another folder for the new installation.

When you have selected the wrong installation mode, close the installer and retry installation from the beginning.




Do not install WinActor Ver.7 to the folder of WinActor Ver.5 or Ver.6.



For information on the handover of node-locked license of WinActor Ver.5 or Ver.6, see "3.4 Steps for registering a license by copying from Ver.5 or Ver.6."


If the specified folder already exists, a confirmation dialog to overwrite the existing folder is displayed.

Click the 'Yes' button to update to a new version of WinActor Ver.7.



If you click the 'No' button, you will return to Step 5 (specifying a folder to install WinActor).

- 6.** Select the license type to apply using the radio buttons, and click the 'Next' button.



 For license types, see "2.2 Checking the license type."

A step to select additional tasks will be displayed.


The dialog to specify the start menu folder will be shown.

When overwriting the preexisting WinActor installed with the license type different from the type selected at this step, the installation of WinActor may display the dialog of the message *The destination of WinActor and License Type ...*

When you install the WinActor of another license type, set another folder for the new installation.


When you have selected the wrong license type, close the installer and retry installation from the beginning.

7. Select whether to associate scenario filename extensions with WinActor. After that, click the 'Next' button.



A step to confirm the installation details will be displayed.


8. Check the details and click the 'Install' button.



The installation progress will be displayed.




It may take about 10 minutes to complete the installation.



When the installation is completed, the following completion window appears.

9. Click the 'Finish' button.



1.2 Installer with manual

When Internet connectivity is unavailable on the environment WinActor is going to be used, install WinActor with the installer with manual.


When WinActor is installed with the installer with manual, the manuals of WinActor are installed in addition to WinActor itself.

The installation procedure is the same as that of the installer without manual. See “1.1.1 Installation method for administrator” or “1.1.2 Installation method for standard user.”

After the installation, you can verify the manual installation with the following procedure.

Steps

1. Open the WinActor installation folder.
2. Open the “WinActor_Documents” folder and the “English” folder in it consecutively.



The PDF files of manuals are deployed as this image.

1.3 Association of scenario files

The WinActor Ver.7 installer associates the filename extensions ums7 and uss7 with WinActor.

The filename extensions of the former versions (ums5 and ums6) cannot be associated.

If you want to associate ums5 or ums6 with WinActor Ver.7, do it manually by using OS functions.



If the check box of "Associate the filename extensions of ums7 and uss7 with WinActor" is unchecked on the dialog of 'Select Additional tasks' in the installation of WinActor for standard user, ums7 and uss7 will not be associated.

1.4 Disassociation of scenario files

This section describes the procedure to disassociate the filename extensions ums7 and uss7.

If there is no need to disassociate, this step is unnecessary.



Follow these steps only if you need to disassociate the filename extensions.

Only the installer of WinActor Ver.7.1 or later supports disassociation.


Steps

1. Start Command Prompt.
2. At the Command Prompt, move to the folder where the WinActor installer is located.
Command example: When the installer is placed on the desktop


```
> cd C:\Users\Username\Desktop\WinActor_v711\WinActor_Installer
```
3. Run the installer with the option "/DELEXTASSOC" to disassociate the extension.
Command example:

```
> WinActorSetup.exe /DELEXTASSOC
```
4. If the User Account Control dialog appears, click the 'Yes' button.

5. If the 'Select Setup Language' dialog appears, select English and click the 'OK' button.



6. If the disassociation is successful, the dialog "Unassociated the filename extensions of ums7 and uss7 successfully." will be displayed.



1.5 Virtual keyboard driver for canceling the screen saver


1.5.1 Install the driver

To use the function of canceling the screen saver, install the virtual keyboard driver which comes with WinActor.

- Installation of the driver for administrator

Installing WinActor for administrator, you can install the virtual keyboard driver and WinActor at once.

Check the “[screen-saver unlocker] Install the Virtual HID Driver” checkbox in the “Select Additional Tasks” of WinActor installation wizard, and install WinActor.




Even if you do not install the virtual keyboard drive and WinActor at once, you can still install the driver independently following the procedure in the next page.


- Installation of the driver for standard user

Steps


1. From the folder WinActor is installed, open “drivers,” and “virtualhid” consecutively. Then, open the folder in accordance with your Windows OS.
For 64bit OS, open the [x64] folder.
For 32bit OS, open the [x86] folder
After that, right-click “installdriver.exe” and select ‘Run as administrator’ to start installation.




2. Click the ‘Yes’ button when ‘User Account Control’ dialog is displayed.
If username and password for administrator are required, enter them and click the ‘Yes’ button.




3. The dialog shown below will be displayed when the installation is successful. Click OK button.



4. Open 'Control Panel,' 'System and Security,' 'System,' and 'Device Manager' consecutively. Confirm that the item WinActor is added.



Seeing "for standard user" in the 'About WinActor' window, you can confirm that WinActor for standard user is installed.



1.5.2 Uninstall the driver


- Uninstallation of the driver for administrator

The virtual keyboard driver will be uninstalled at once when you uninstall WinActor for administrator.


- Uninstallation of the driver for standard user

Steps


1. From the folder WinActor is installed, open “drivers,” and “virtualhid” consecutively. Then, open the folder in accordance with your Windows OS.
For 64bit OS, open the [x64] folder.
For 32bit OS, open the [x86] folder
After that, right-click “removedriver.exe” and select ‘Run as administrator’ to start uninstallation.




2. Click the 'Yes' button when 'User Account Control' dialog is displayed.
If username and password for administrator are required, enter them and click the 'Yes' button.



3. The dialog shown below will be displayed when the uninstallation is successful.
Click the 'OK' button.



4. Open 'Control Panel,' 'System and Security,' 'system,' and 'Device Manager' consecutively. Confirm that the item WinActor is removed.



The virtual keyboard driver will remain undeleted even if you remove the folder into which WinActor is installed.

Follow the procedure in this section to remove the virtual keyboard driver before you remove the folder into which WinActor is installed.

1.6 Manual installer

When Internet connectivity is available, a manual is automatically downloaded on opening it from a link on the welcome window.


When manuals are necessary but the WinActor has been installed on an environment without Internet connectivity with the installer without manual, use the manual installer to install all the manuals.

1.6.1 Installing manuals

Here, all the manuals are being installed using the manual installer.

Steps


1. Start the installer “Winactor_ManualInstaller.exe” in the folder “Manual_Installer.”



The WinActor manual setup program will be launched.

2. The selection dialog of installation modes is displayed.


When the 'WinActor for administrator' has been selected on the 'Select Setup Install Mode' dialog during the installation of the WinActor, click the "Install manuals for 'WinActor for administrator.'" When the 'WinActor for standard user' has been selected, click the "Install manuals for 'WinActor for standard user.'"




When the "Install manuals for 'WinActor for administrator'" is clicked, 'User Account Control' dialog will be displayed.

When the "Install manuals for 'WinActor for standard user'" is clicked, 'Select Setup Language' dialog will be displayed.

3. Click the 'Yes' button when 'User Account Control' dialog is displayed.




4. When the 'Select Setup Language' dialog appears, select English and click the 'OK' button




5. Installation destination will be automatically determined, but sometimes the dialog to specify the destination is displayed depending on the environment.

Specify the destination folder "WinActor_Documents" to install WinActor for the dialog and click the 'Next' button.



The confirmation dialog of the installation will be displayed.


6. Check the details on the dialog and click the 'Install' button.



The installation progress will be displayed.




It may take about 10 minutes to complete the installation.



When the installation is completed, the following completion window appears.

7. Click the 'Finish' button.



2. Launching WinActor

This chapter describes how to launch WinActor and how to check its license after launching.

2.1 Launching WinActor

Double-click the "WinActor7" icon placed on the desktop or "WinActor7.exe" under the WinActor folder.




When there is no WinActor startup icon on the desktop:


- When a shortcut was not created on the desktop during the installation: Launch WinActor7 from the Windows Start Menu.
 - When WinActor for standard user is installed, launch WinActor by double-clicking WinActor7.exe in the folder where WinActor is installed.
-

The end user license agreement is displayed at the first startup depending on the execution environment.


Read through the entire end user license agreement when it is displayed, and click the 'Agree' button.



WinActor launches and the following "Welcome page" appears.



If WinActor is running as an evaluation edition, the following window will be displayed. If you want to use it as a product edition, you need to set a license described in the following section.



2.2 Checking the license type

There are three types of WinActor licenses: Node-locked license, Floating license, and AI integration license.

- Node-locked license (abbreviated as NL)

This license is managed on a computer where WinActor is installed.

 For the node-locked license, see "3 [NL] License registration" to register the license.

- Floating license (abbreviated as FL)

This license is managed on the floating-license-management server.

 For the floating license, see "5 [FL] Setting the license server connection information" to set the license.

- AI integration license (abbreviated as AL)

This license is managed on the AI-integration-license-management server.

The AI-integration-license-management server is provided by NTT-AT.

This license enables using AI integrated functions without additional contracts with a Generative AI vendor.

 For the AI integration license, see "6 [AL] AI integration license server connection settings" to set the license.

2.2.1 Display differences among license types

The license type of the installed WinActor can be checked on the 'About WinActor' dialog, on the 'Option' dialog, and on the launcher window as shown in the table below.

Table 2.-1 Window displays by license type ('About WinActor' dialog)




	Launcher
Node-locked license	'Register a license' button exists. 
Floating license	"FL" exists at the end of the version information. 
AI integration license	"AL" exists at the end of the version information. 

Table 2.-2 Window displays by license type ('Option' dialog)





	Launcher
Node-locked license	No 'License server' tab exists. 'AI integration license server' tab does not exist. 
Floating license	'License server' tab exists. 'AI integration license server' tab does not exist. 
AI integration license	'License server' tab does not exist. 'AI integration license server' tab exists. 

Table 2.-3 Window displays by license type (Launcher)

	Launcher
Node-locked license	Bluish background color  Red color icon
Floating license	Reddish background color  Blue color icon
AI integration license	Reddish background color  Yellow color icon


2.2.2 Displaying the About WinActor dialog

You can display the 'About WinActor' dialog from 'Help' > 'Version' on the menu bar.



2.2.3 Displaying the Option dialog

You can display the 'Option' dialog from 'Tool' > 'Option' on the menu bar.



3. [NL] License registration

This chapter describes the procedure of the license registration for a node-locked license.

If you use the evaluation edition of WinActor, the steps in this chapter are not necessary.

You can register a node-locked license either online, via the WinActor license issuance site, or via a WinActor agency.



“3.1 Online license registration”



“3.2 License registration via WinActor license issuance site”



“3.3 License registration via agency”

If you are using a node-locked license for WinActor Ver.5 or Ver.6, you can use the same license for Ver.7, and the steps in this chapter are not necessary. Proceed to the steps for registering a license by copying from Ver.5 or Ver.6.



“3.4 Steps for registering a license by copying from Ver.5 or Ver.6”

3.1 Online license registration

This section describes the procedure of registering a license online.

Once you complete registering a license online, you do not need to register it via a WinActor agency.




- Making a new license contract, you can use WinActor by registering the license online on or after the starting date of the license contract.
Renewing a license contract, you can continue using WinActor by registering the renewed license online prior to the termination date of the previous license contract.




Settings on the 'Proxy server' tab in the 'Option' dialog are necessary for the network environment using a proxy server. See "WinActor operation manual" for the settings.

Steps


1. After launching WinActor, click 'Help' > 'Version' on the menu bar.



- 2.** The 'About WinActor' dialog appears.
Click the 'License registration' button.



- 3.** The dialog to select a license registration method is displayed.
Click the 'Online' button to register a license online.



4. The 'Online license registration' dialog is displayed. Carefully input 'Support ID,' 'Termination date of the support period,' and 'License type' of edition. Also, input a name for 'PC name.'

To notify the agency of the license issuance via e-mail, check the 'E-mail notification to the agency,' and input 'E-mail address of the agency,' 'User name,' and 'Company name of the user.'

Then, push 'Register' button.

Online license registration

Fill the boxes below and click 'Register' button to get a new license issued. When the 'Register' button is clicked, the communication with the server (https://) starts.

Check twice the 'Support ID', the 'License type', and the 'Termination date of the support period' to avoid an error. Specify any name that is unique in your environment for the "PC name".

Support ID

Termination date of the support period

yyyy-mm-dd 15

License type

☒ FULL edition ☐ RUN edition

PC name (input arbitrary name)

TEST

☐ E-mail notification to the agency

E-mail address of the agency


User name

Company name of the user


Register Cancel

- 5.** When the license registration succeeds, the following dialog is displayed.

Click the 'OK' button to relaunch WinActor and to reflect the registered license,




- 6.** Click the 'OK' button again to relaunch WinActor.



7. Click 'Version' under 'Help' menu of the 'menu' bar on relaunched WinActor to display 'About WinActor' dialog.

When "Running under Product license" is displayed, the license registration is completed.



3.2 License registration via WinActor license issuance site

The procedure of registering a license via the WinActor license issuance site is described in this section.



- In every procedure of the license issuance, renewal, and transfer, the support ID information printed on the “Robotic Process Automation Software WinActor Support ID Notification” is necessary. Before application, please have it on hand.
 - For the ‘license issuance’ procedure to be carried out at the first contract, or the ‘license renewal’ procedure to be carried out at the time of the contract renewal, follow the procedure described in “3.2.1 License issuance and renewal.”
Customers who concluded a new contract can use WinActor by applying for the ‘license issuance’ and registering the issued license file on WinActor after the start date of the support period.
Customers who renewed the contract can continue using WinActor by applying for the ‘license renewal’ and registering the renewed license file on WinActor before the termination date of the previous support period.
Record the PC (Product ID) for which you applied for the license issuance or renewal.
 - When the major version number of WinActor is upgraded (e.g., 4.3.2→5.2.1), make a new contract and apply for the ‘license issuance.’
However, when upgrading from Ver.5 or Ver.6 to Ver.7, proceed with the procedure, referring “3.4 Steps for registering a license by copying from Ver.5 or Ver.6.”
When the minor version number of WinActor is updated (e.g., 5.1.3→5.2.1), ‘license issuance’ is not necessary.
 - Apply for the ‘license transfer’ when the PC or the OS on which WinActor is installed is broken or replaced.
The ‘license transfer’ is carried out not by support ID but by license
Carry out the transfer procedure, contacting your agency and referring “4.2 License transfer via WinActor license issuance site.”
 - If you have any trouble in carrying out the license issuance, renewal, or transfer procedure, or if you have points to be cleared, contact your agency.
-

3.2.1 License issuance and renewal

Carry out the 'license issuance' or 'license renewal' procedure when applying for a license at the first time or renewing a license at the time of the contract renewal.

Steps

1. Connect to the WinActor license issuance site, and display the "WinActor license application form."



The screenshot shows the WinActor logo at the top left. To the right is a language dropdown menu with 'English' selected. Below the logo, the text reads: "This is the page to apply for WinActor license issuance. For the procedure of the WinActor license issuance, refer to the "WinActor Installation Manual." To apply for WinActor license transfer, click [here](#). To refer for example of WinActor license certificate, click [here](#)." At the bottom, there is a button labeled "WinActor license application form".



If the site is not displayed in English, select 'English' in the dropdown.




The screenshot shows the WinActor logo. To the right is a language dropdown menu with '日本語' (Japanese) selected. Below the logo, the text is in Japanese: "は、WinActorのライセンスを発行するページです。手順についてはWinActorインストールマニュアルをご参照ください。イセンス移管手続きは、[こちら](#)からご利用いただけます。イセンス証書との対比は、[こちら](#)をご参照ください。" At the bottom, there is a button labeled "WinActorライセンス発行 手続きフォーム".

2. Enter the 'Support ID.'



The screenshot shows a text input field labeled "Support ID". The field contains the text "XXXXXXXXXX".

3. Select the 'License type' of edition from the dropdown.



The screenshot shows a dropdown menu labeled "License type". The menu is open, showing three options: "FULL edition", "FULL edition", and "RUN edition". The first "FULL edition" option is highlighted.

4. Enter the 'Termination date of the support period.'

Termination date of the support period
12/31/2025

Identification name of the user PC
WinActorPC

Product ID

☐ Notify the agency of the license

© 2025 WinActor is a trademark of Nippon Advanced Technology Corporation, registered in Japan, the U.S.,




If any of the entered 'Support ID,' 'License type,' and 'Termination date of the support period' is invalid, an error occurs. Confirm every input to avoid an error as it needs you to restart the procedure from the first step.

5. Enter 'Identification name of the user PC such as the PC name.'

Identification name of the user PC such as the PC name
WinActorPC

6. Enter 'Product ID.'

- (1) Click 'Help(H)' and 'Version' from the WinActor menu bar consecutively.




'About WinActor' dialog is displayed.




'About WinActor' dialog can be displayed even if the evaluation expiration date of the Evaluation license has passed.

- (2) Click the 'Copy Product ID to clipboard' button.



The product ID is copied to the clipboard.


- (3) Paste the copied product ID into the 'Product ID' box.






Product ID can be entered by dragging and dropping the 'Product ID file' into the 'Product ID' box. The procedure is described below.


- (1) Click the 'Save Product ID' button to create a 'Product ID file.'



- (2) The initial filename is "WinActorProductID_XXXXXXXX.txt" where "XXXXXXXX" is some alphanumeric letters. Click the 'Save' button.



- (3) Drag and drop the 'Product ID file' into the 'Product ID' box.





When the PC to use WinActor is different from the PC to input the application form, click the 'Save Product ID' button on the PC to use WinActor, and create a 'Product ID file'.

Copy the 'Product ID file' to the PC to input the application form, and carry out either of the following procedures.

1. Copy the contents of the 'Product ID file' to the clipboard, and paste it into the 'Product ID' box.
2. Drag and drop the 'Product ID file' into the 'Product ID' box.

7. When the notification to the agency is preferred, check the "Notify the agency of the license issuance by e-mail" box.

The screenshot shows a web form with the following elements:

- A checkbox labeled "Notify the agency of the license issuance by e-mail." which is checked and highlighted with a blue border.
- A text input field labeled "E-mail address1 of the agent (e-mail address to notify)".
- A button with a "+" sign and a "-" sign next to the email field.
- A text input field labeled "The name of the user".
- A text input field labeled "The company name of the user".
- A section titled "About the agreement on the handling of personal information *Required to read".
- A paragraph of text: "About the handling of personal information, refer to [the PRIVACY POLICY page](#) of our company site."
- A checkbox labeled "Agree".



If the notification to the agency is not necessary, this step can be omitted. Jump to the step [10](#) in such case.

8. Enter 'E-mail address of the agent (e-mail address to notify),' 'The name of the user,' and 'the company name of the user.'

Up to 3 e-mail addresses of the agency can be entered.

A screenshot of a web form for license issuance. At the top, there is a checked checkbox labeled "Notify the agency of the license issuance by e-mail." Below this, there are three input fields. The first field is labeled "E-mail address1 of the agent (e-mail address to notify)" and contains the text "XXXXXX@example.com". The second field is labeled "The name of the user" and contains "XXXX XXXX". The third field is labeled "The company name of the user" and contains "XXXXXXXX Ltd.". To the right of the first field, there are "+" and "-" buttons for adding or removing email addresses.



Check the e-mail address very carefully because entering a wrong address may cause a notification failure or an incident of notifying to an outside person.



The agency is notified of the result whether the license issuance to the user is successful or not.

Input errors of the information printed on the "Robotic Process Automation Software WinActor Support ID Notification" will not be notified to the agency.

9. Read through the "PRIVACY POLICY" page, and check the 'Agree' box.

A screenshot of a privacy policy agreement section. It contains the text "About the agreement on the handling of personal information *Required to read" and "About the handling of personal information, refer to [the PRIVACY POLICY page](#) of our company site." Below this text, there is a checkbox labeled "Agree" which is checked.

10. Click the 'License issuance' button after confirming the input contents are correct.

A screenshot of the bottom of the form. It features a blue button labeled "License issuance". Below the button, the footer text reads: "© 2024 NTT Advanced Technology Corporation", "WinActor is a trademark of NTT Advanced Technology Corporation, registered in Japan, the U.S., China, EU and other countries and regions."

The 'Download license file' page is displayed.

11. Click the 'Download' button, and download the license file. Place the license file under the "Documents" folder of the PC WinActor is installed.

Record the 'Receipt number' and the contents of application as the application history.



WinActor license application form

A new license is issued.

Click the 'Download' button to download the license file.

Download license file [↓ Download](#)

For the procedure of WinActor license registration, refer to the "WinActor Installation Manual."

Receipt number: AB-CDEFGHIJK

Support ID	XXXXXXXXXX
Termination date of the support period	2025-12-31
License type	FULL edition
Number of licenses used	1
Total number of licenses	10



The same license file can be downloaded again if the same product ID (after transfer in the case of transferring a license) is used in application form. Make use of this technique when the download failed, or the downloaded file is lost.



WinActor license application form

The license that corresponds to the product ID has already been issued.

To redownload the license file that has already been issued, click the 'Download' button.

Download license file [↓ Download](#)

For the procedure of WinActor license registration, refer to the "WinActor Installation Manual."

Receipt number: AB-CDEFGHIJK

Click 'here' to continue license applications.

To issue additional licenses, click [here](#).

Please fill out the questionnaire to help improve future WinActor products.
We appreciate your opinion without reserve.
[Questionnaire survey of WinActor products](#)

© 2024 NTT Advanced Technology Corporation

WinActor is a trademark of NTT Advanced Technology Corporation, registered in Japan, the U.S. ,
China, EU and other countries and regions.

[Return to top page](#)



An error message is displayed when the license application failed for a reason such as faults in the application contents.



WinActor license application form

The license issuance failed. Confirm the support ID, the license type, and the termination date of the support period printed on the "Robotics Process Automation Software Support ID Notification," and try again. If this does not work, contact the agency with the application content, the error message, and the receipt number.

Status : 400 / Error code : 105
Receipt number: AB-CDEFGHIJK

Following the instructions in the error message, restart the application procedure from the first step.

When the server causes the error, the 'Retry' button is displayed. Try clicking the 'Retry' button after a while.



WinActor license application form

The license issuance failed. Wait a while, and try again. If this does not work, contact the agency with the application content, the error message, and the receipt number.

Status : 500 / Error code : 203
Receipt number: AB-CDEFGHIJK

Retry

- 12.** From the link “Questionnaire survey of WinActor products,” answers to the questions can be entered. We deeply appreciate your answers to improve WinActor products.

Please fill out the questionnaire to help improve future WinActor products.
We appreciate your opinion without reserve.
[Questionnaire survey of WinActor products](#)

- 13.** Following the same steps as ‘3.3.3 License registration steps,’ register the issued license file for WinActor.

 “3.3.3 License registration steps”

3.3 License registration via agency


This section describes the procedure for license registration via a WinActor agency.

3.3.1 License issuance request

This section describes the steps for sending a product ID file for license issuance.


Steps

1. After launching WinActor, click 'Help' > 'Version' on the menu bar.




The 'About WinActor' dialog appears.


2. Click the 'Save Product ID' button.



The initial filename is "WinActorProductID_XXXXXXXX.txt (XXXXXXXX is alphanumeric characters)." Click the 'Save' button.




3. Send an email to the agency you purchased WinActor for license issuance. Make sure to attach the saved product ID file.



3.3.2 Obtaining a license file

A license file will be sent from the agency as a reply to your license issuance request email. The figure below is an example of the reply.

Place the attached license file under the "Documents\WinActor" folder on the computer where WinActor is installed.




3.3.3 License registration steps


Register a license with the following steps.

Steps


1. After launching WinActor, click 'Help' > 'Version' on the menu bar.




2. The 'About WinActor' dialog appears. Click the 'Register a license' button.



3. The dialog to select a license registration method is displayed. Click the 'Local file' button to register a license from a local file.



4. The window of 'Select a license file' appears. Select a license file and click the 'Open' button.




The license file "WinActorLicense_XXXXXXXX.txt (XXXXXXXX is alphanumeric characters)" will be loaded.




An error occurs if the license file cannot be found in the "Documents\WinActor" folder or if the license is registered on a computer different from the one the "Product ID file" is generated.

5. Once the license file is loaded successfully, the dialog to inform completion of the license registration appears. Click the 'OK' button to restart and reflect the license.




6. Click the 'OK' button again to relaunch WinActor.



7. Click 'Help' > 'Version' on relaunched WinActor to display the 'About WinActor' dialog.

When "Running under Product license." is displayed, the license registration is completed.




- Error when registering a license

If "Failed to read license file." or "The license file is invalid." is displayed during license registration, the license may have been registered on a computer with a different product ID.

In that case, click the 'Save Product ID' button on the 'About WinActor' dialog and output the product ID file.

Confirm whether the alphanumeric characters assigned to the product ID filename and license filename match as shown in the figure below.



3.4 Steps for registering a license by copying from Ver.5 or Ver.6

If you are using the node-locked license for WinActor Ver.5 or Ver.6, you can use the same license for Ver.7.


If the node-locked version of WinActor Ver.5 or Ver.6 has been installed using the **installer for administrator**, the node-locked version of Ver.7 can be used as it is, and the steps in this chapter are not necessary.

Click 'Help' > 'Version' on the menu bar, and confirm that "Running under Product License." is displayed on the 'About WinActor' dialog.

If the node-locked version of WinActor Ver.5 or Ver.6 has been installed using the **installer for standard user**, register the license according to the following steps.


Steps

1. After launching WinActor, click 'Help' > 'Version' on the menu bar.




The 'About WinActor' dialog appears.

2. Click the 'Register license by copying ver.5 or ver.6 license' button.



The confirmation dialog appears.


3. Click the 'OK' button.




The WinActor.exe file selection window appears.

4. Select the WinActor.exe or OR-5200.exe file located in the folder where WinActor Ver.5 or Ver.6 or OR-5200 is installed.


Click the 'Open' button to register the license.




5. Click the 'OK' button.



6. Click the 'OK' button.




7. Click the 'OK' button.



WinActor restarts.

8. After the restart, click 'Help' > 'Version' to display the 'About WinActor' dialog and confirm that "Running under Product license." is displayed.



4. [NL] License transfer

This chapter describes the procedure of transferring a node-locked license.

The license needs to be transferred when the computer on which WinActor is installed is broken, when OS on the computer or the computer itself needs to be replaced, and so on.

Each license needs to be transferred separately, not by a unit of a maintenance ID.

Consult the agency you purchased your WinActor in advance and follow the steps below to transfer the license.



- Do not uninstall WinActor from your computer before transferring the license.
-

You can transfer a node-locked license online, via WinActor license issuance site, or via a WinActor agency.



"4.1 Online license transfer"

"4.2 License transfer via WinActor license issuance site"

"4.3 License transfer via agency"

4.1 Online license transfer

This section describes the procedure of transferring a license online.


Once you complete transferring a license online, you do not need to transfer it via a WinActor agency.




Settings on the 'Proxy server' tab in the 'Option' dialog are necessary for the network environment using a proxy server. See "WinActor operation manual" for the settings.

Steps


1. After launching WinActor, click 'Help' > 'Version' on the menu bar.




- 2.** The 'About WinActor' dialog appears.
Click the 'Clear license' button.



- 3.** The dialog to confirm the license clearance is displayed.
Confirm it and click the 'OK' button.




4. A dialog to select whether to notify the server of the license clearance or not is displayed. Click the 'Yes' button to transfer the license online.




5. The dialog to save the product ID file and the WinActor license clearance certificate file is displayed.

Click the 'OK' button.




6. The 'Save WinActor Product ID' window is displayed. The initial filename is "WinActorProductID_XXXXXXX.txt," in which XXXXXXXX is alphanumeric characters. Specify a folder to save the file and click the 'Save' button. The product ID file will be saved.



7. 'Save WinActor license clearance certificate file' dialog is displayed. Select a folder to save the file, and click the 'Save' button.


The license is cleared, and the WinActor license clearance certificate file is saved.




Click the 'Cancel' button on the 'Save WinActor Product ID' or the 'Save WinActor license clearance certificate file' window to cancel the operation of the license clearance.

8. When the online notification of the license clearance succeeds, the dialog to inform the completion of notifying the server is displayed.

Click the 'OK' button.



When the dialog to inform the failure of notifying the server of the license clearance is displayed, the online notification is failed.



In that case, please consult your WinActor agency and transfer the license via the agency.

>> "4.3 License transfer via agency"

9. Register the license on the new computer. The registration procedure is the same as the 'Online license registration.'

>> "3.1 Online license registration"

4.2 License transfer via WinActor license issuance site

The procedure of transferring a license on the WinActor license issuance site is described here.

Steps

1. Connect to the WinActor license issuance site, and display the “WinActor license transfer application form” page via the anchor ‘here’ in the “To apply for WinActor license transfer, click here.” displayed at the top of the “WinActor license application form” page.



The screenshot shows the WinActor logo at the top left. To its right is a language dropdown menu currently set to 'English'. Below the logo, the text reads: 'This is the page to apply for WinActor license transfer. For the procedure of the WinActor license transfer, refer to the "WinActor Installation Manual." To apply for WinActor license issuance, click [here](#). To refer for example of WinActor license certificate, click [here](#).' At the bottom of the page, there is a green banner with the text 'WinActor license transfer application form'.



If the site is not displayed in English, select 'English' in the dropdown.




The screenshot shows the WinActor logo at the top left. To its right is a language dropdown menu with options for '日本語' (Japanese) and 'English'. The 'English' option is highlighted. Below the logo, the text is in Japanese: 'WinActorのライセンス移管手続きをするページです。手順についてはWinActorインストールマニュアルをご参照ください。イセンス発行手続きは、[こちら](#)からご利用いただけます。イセンス証書との対比は、[こちら](#)をご参照ください。' At the bottom of the page, there is a green banner with the text 'WinActorライセンス移管 手続きフォーム'.



Both the product ID before transfer and the product ID after transfer acquired from respective PCs are necessary. Follow the procedure described below.

2. Enter the 'Support ID.'




The screenshot shows the WinActor logo at the top left. Below the logo, there is a green banner with the text 'WinActor license transfer application form'. Below the banner, there is a text input field labeled 'Support ID' with the placeholder text 'XXXXXXXXXX'.

3. Select the 'License type' of edition from the dropdown.



A screenshot of a software interface showing a dropdown menu for 'License type'. The menu is open, displaying three options: 'FULL edition', 'FULL edition', and 'RUN edition'. The first 'FULL edition' option is highlighted with a blue border.

4. Enter the 'Termination date of the support period.'




A screenshot of a software interface showing a date selection field. The field is labeled 'Termination date of the support period' and contains the date '12/31/2025'. A calendar pop-up is displayed, showing the month of December 2025. The date '31' is selected, highlighted in blue. The calendar shows days of the week (Mo, Tu, We, Th, Fr, Sa, Su) and dates from 1 to 31. Below the calendar, there are several input fields: 'Identification name of the user', 'Product ID before transfer', 'Product ID after transfer', and 'Purpose of the license transfer'. A green banner at the bottom right of the interface states 'Clearance certificate is not available.'



If any of the entered 'Support ID,' 'License type' of edition, and 'Termination date of the support period' is invalid, an error occurs. Confirm every input to avoid an error as it needs you to restart the procedure from the first step.


5. Enter 'Identification name of the user PC after transfer such as the PC name.'



A screenshot of a software interface showing an input field for 'Identification name of the user PC after transfer such as the PC name'. The field contains the text 'WinActorPC'.


6. Save 'Product ID' and 'License clearance certificate' into files.

- (1) On the PC before transfer, click 'Help(H)' and 'Version' from the WinActor menu bar consecutively.




'About WinActor' dialog is displayed.

- (2) Click the 'Clear license' button.




The confirmation dialog of clearing license is displayed.


- (3) Click the 'OK' button on the confirmation dialog of clearing license.




- (4) The dialog to select whether to notify the server online of the license clearance is displayed.
Click 'No' as this is a license transfer procedure on the WinActor license issuance site.




- (5) The dialog to prompt saving the product ID and the license clearance certificate is displayed. Click the 'OK' button.



- (6) The 'Save WinActor Product ID' dialog is displayed.
The initial filename is "WinActorProductID_XXXXXXX.txt," where XXXXXXXX is alphanumeric letters. Select a folder to save the file, and click the 'Save' button.
The 'Product ID file' is saved.




- (7) The 'Save WinActor license clearance certificate file' dialog is displayed.
Save the 'License clearance certificate' into a folder.



The completion dialog of saving the license clearance certificate file is displayed.

- (8) Click the 'OK' button on the completion dialog.




The 'License clearance certificate' is saved as a file of the filename "WinActorClearLic_XXXXXXXX.txt," where "XXXXXXXX" is alphanumeric letters.




If the license clearance certificate cannot be output, write out the reason in "The reason why you cannot obtain the license clearance certificate text" box at the step 10 below, and you can proceed the license transfer procedure.
e.g., My PC has broken, and cannot output the certificate.

- 7.** Enter the 'Product ID' before license transfer into the box 'Product ID before transfer.' Copy the content of the 'Product ID file' saved at the step 6 to the clipboard, and paste it or drag and drop the saved 'Product ID file' into the 'Product ID before transfer' box.



- 8.** Enter 'Product ID after transfer.'

- (1) On the PC after transfer, click 'Help(H)' and 'Version' from the WinActor menu bar consecutively.




'About WinActor' dialog is displayed.




'About WinActor' dialog can be displayed even if the evaluation expiration date of the Evaluation license has passed.

- (2) Click the 'Copy Product ID to clipboard' button.



The product ID is copied to the clipboard.


- (3) Paste the product ID copied to the clipboard into the 'Product ID after transfer' box.






Product ID can be entered by dragging and dropping the 'Product ID file' into the 'Product ID after transfer' box. The procedure is described below.

- (1) Click the 'Save Product ID' button to create a 'Product ID file.'



- (2) The initial filename is "WinActorProductID_XXXXXXX.txt" where "XXXXXXX" is some alphanumeric letters. Click the 'Save' button.



- (3) Drag and drop the 'Product ID file' into the 'Product ID after transfer' box.





When the PC to use WinActor is different from the PC to input the application form, click the 'Save Product ID' button on the PC to use WinActor, and create a 'Product ID file'.

Copy the 'Product ID file' to the PC to input the application form, and carry out either of the following procedures.

1. Copy the contents of the 'Product ID file' to the clipboard, and paste it into the 'Product ID after transfer' box.
2. Drag and drop the 'Product ID file' into the 'Product ID after transfer' box.

9. Enter 'Purpose of the license transfer.'

Purpose of the license transfer
Changing PC

10. Enter 'License clearance certificate.'

Copy the content of the 'License clearance certificate file' saved at the step 6 to the clipboard, and paste it or drag and drop the saved 'License clearance certificate file' into the 'License clearance certificate' box.

The license clearance certificate is not available.

License clearance certificate
86CA53E6E440E1F6B26C833DFEED95FA16B3E6FBB2B82FD0CCB12F824B543FDF01BF81
1ED4127E85D8EB56D5E1039121029549ECBC14EC86E04BEB82D6CA4D5753664E44E9AD



If the license clearance certificate cannot be output for unavoidable reason, check "The license clearance certificate is not available" box. To proceed the license transfer procedure, write out the reason why the license clearance certificate cannot be output in "The reason why you cannot obtain the license clearance certificate text" box.

☒ The license clearance certificate is not available.

The reason why you cannot obtain the license clearance certificate text
My PC has broken, and cannot output the certificate.

- 11.** When the notification to the agency is preferred, check the “Notify the agency of the license issuance by e-mail” box.

☒ Notify the agency of the license issuance by e-mail.

E-mail address1 of the agent (e-mail address to notify)

+ -

Name of the user

Company name of the user

About the agreement on the handling of personal information *Required to read

About the handling of personal information, refer to [the PRIVACY POLICY page](#) of our company site.

☐ Agree



If the notification to the agency is not necessary, this step can be omitted.
Jump to the step [14](#) in such case.

- 12.** Enter ‘E-mail address of the agent (e-mail address to notify),’ ‘The name of the user,’ and ‘the company name of the user.’

Up to 3 e-mail addresses of the agency can be entered.

☒ Notify the agency of the license issuance by e-mail.

E-mail address1 of the agent (e-mail address to notify)

XXXXX@example.com

+ -

Name of the user

XXXX XXXX

Company name of the user

XXXXXXXX Ltd.



Check the e-mail address very carefully because entering a wrong address may cause a notification failure or an incident of notifying to an outside person.



The agency is notified of the result whether the license transfer by the user is successful or not.

Input errors of the information printed on the “Robotic Process Automation Software WinActor Support ID Notification” will not be notified to the agency.

13. Read through the “PRIVACY POLICY” page, and check the ‘Agree’ box.

About the agreement on the handling of personal information *Required to read

About the handling of personal information, refer to [the PRIVACY POLICY page](#) of our company site.

☒ Agree

14. Click the ‘License transfer’ button after confirming the input contents are correct.

License transfer

© 2024 NTT Advanced Technology Corporation

WinActor is a trademark of NTT Advanced Technology Corporation, registered in Japan, the U.S. ,
China, EU and other countries and regions.

The ‘Download license file’ page is displayed.

- 15.** Click the 'Download' button, and download the license file. Place the license file under the "Documents" folder of the PC WinActor is installed. Record the 'Receipt number' and the contents of application as the application history.



WinActor license transfer application form

The license has been transferred.

Click the 'Download' button to download the license file.

Download license file ↓ Download

For the procedure of WinActor license registration, refer to the "WinActor Installation Manual."

Receipt number: AB-CDEFGHIJK

Support ID	XXXXXXXXXX
Termination date of the support period	2025-12-31
License type	FULL edition
Number of licenses used	1
Total number of licenses	10



The same license file can be downloaded again if the same product ID (after transfer in the case of transferring a license) is used in the application form. Make use of this technique when the download failed, or the downloaded file is lost.



WinActor license application form

The license that corresponds to the product ID has already been issued.

To redownload the license file that has already been issued, click the 'Download' button.

Download license file ↓ Download

For the procedure of WinActor license registration, refer to the "WinActor Installation Manual."

Receipt number: AB-CDEFGHIJK

Click the 'Return to top page' to continue license transfer applications.

© 2024 NTT Advanced Technology Corporation

WinActor is a trademark of NTT Advanced Technology Corporation, registered in Japan, the U.S. ,
China, EU and other countries and regions.

[Return to top page](#)



An error message is displayed when the license transfer application failed for a reason such as faults in the application contents.

 WinActor®

WinActor license transfer application form

The specified license clearance certificate is invalid. Confirm the license clearance certificate obtained at the clearance of the license on the PC before transfer, and try again. For the details of the license transfer procedure, refer to the "WinActor Installation Manual." If this does not work, contact the agency with the application content, the error message, and the receipt number.

Status : 400 / Error code : 014
Receipt number: AB-CDEFGHIJK

Following the instructions in the error message, restart the application procedure from the first step.

When the server causes the error, the 'Retry' button is displayed. Try clicking the 'Retry' button after a while.

 WinActor®


WinActor license transfer application form

The license issuance failed. Wait a while, and try again. If this does not work, contact the agency with the application content, the error message, and the receipt number.

Status : 500 / Error code : 203
Receipt number: AB-CDEFGHIJK

[Retry](#)

- 16.** From the link “Questionnaire survey of WinActor products,” answers to the questions can be entered. We deeply appreciate your answers to improve WinActor products.



- 17.** Following the same steps as '3.3.3 License registration steps,' register the issued license file for WinActor on the PC after transfer.


 "3.3.3 License registration steps"

4.3 License transfer via agency


This section describes the procedure of transferring the license via a WinActor agency. Consult your WinActor agency in advance, and follow the steps.

Steps

1. After launching WinActor on the computer from which the License is transferred, click 'Help' > 'Version' on the menu bar.




2. The 'About WinActor' dialog appears. Click the 'Clear license' button.




- 3.** The dialog to confirm the license clearance is displayed.

Confirm it and click the 'OK' button.




- 4.** A dialog to select whether to notify the server of the license clearance or not is displayed. Click the 'No' button as it is not necessary.




- 5.** The dialog to save the product ID file and the WinActor license clearance certificate file is displayed.

Click the 'OK' button.




6. The 'Save WinActor Product ID' window is displayed. The initial filename is "WinActorProductID_XXXXXXX.txt," in which XXXXXXXX is alphanumeric characters. Specify a folder to save the file and click the 'Save' button. The product ID file will be saved.




7. 'Save WinActor license clearance certificate file' dialog is displayed. Select a folder to save the file, and click the 'Save' button.

The license is cleared, and the WinActor license clearance certificate file is saved.



Click the 'Cancel' button on the 'Save WinActor Product ID' or the 'Save WinActor license clearance certificate file' window to cancel the operation of the license clearance.

Click the 'OK' button on the dialog.




The WinActor license clearance certificate file of the name "WinActorClearLic_XXXXXXXX.txt," in which XXXXXXXX is alphanumeric characters, is saved.


8. Request a license transfer to the agency you have consulted in advance. It would be necessary to submit your WinActor license clearance certificate file, and the product ID files of the cleared computer and the new computer to the agency.



When the new computer is different from the one the license is cleared, click 'Save Product ID' button on the new computer, and create the product ID file.




The initial filename is "WinActorProductID_XXXXXXXX.txt," in which XXXXXXXX is alphanumeric characters. Click 'Save' button, and use the saved product ID file as that of the new computer.



A typical agency would ask you to send an email with the necessary files attached. Follow the procedure of the license issuance request, and remember attaching your WinActor license clearance certificate file and the product ID file of the cleared computer in addition to the product ID file of the new computer in that case.

>> “3.3.1 License issuance and renewal”



A new license file will be sent from the agency typically as a reply to your license transfer request email.

9. Register the new license file on the new computer to transfer the license. The registration procedure is the same as the 'Obtaining a license file' and the 'License registration steps.'

>> “3.3.2 Obtaining a license file”


>> “3.3.3 License registration steps”

5. [FL] Setting the license server connection information

This chapter describes the steps for setting the license server connection information when using a floating license.

Steps

1. Click 'Tool' > 'Option' on the menu bar.



The 'Option' dialog appears.

2. On the 'License server' tab, enter 'URL' and 'Password' for License server 1.

If a client certificate is required to connect to the license server, enter 'Client certificate' and 'Certificate password.'

If the license server has a redundant configuration, enter License server 2 as well.

Option

Log server Run Date and time Log Screen saver Update Browser Misc.
Management server **License server** Proxy server Server connection status

Select edition you want to enable on the next launch.
Set URL for License server to get the license.

☐ FULL edition
☒ RUN edition
☐ Managed RUN edition
☐ Use the same URL as the one for Management server

License server 1 Example: https://192.0.2.0/
URL
Password
Client certificate
Certificate password


License server 2
URL
Password
Client certificate
Certificate password

* When you get a license from License server, the fields of License server 1 are mandatory.
License server 2 is a fallback of License server 1 and its fields are optional.
* Client certificate and Certificate password are required when connecting to the server that requests client certificate.



- The information required to connect to the license server depends on the environment in which you use WinActor. Ask the administrator of the license server for the required information.

3. If you use a proxy server, enter the required information on the 'Proxy server' tab.



Option

Log server Run Date and time Log Screen saver Update Browser Misc.
Management server License server Proxy server Server connection status

☒ Use proxy server

Select how to configure proxy server.

☐ Use your computer's proxy settings

☐ Use OS (WinHTTP) settings

☐ Use setup script(pac)

Script address

☐ Set manually

Address 192.168.0.1

Port 2316

☒ Authentication required

Authentication method Basic/Digest

Username winactor

Password

Domain

OK Cancel



- It supports a proxy server with authentication. Basic authentication, digest authentication, and NTLM authentication are supported.

4. You can check the connection status with the license server by clicking the 'Check connection' button.

Option

Log server Run Date and time Log Screen saver Update Browser Misc.
Management server **License server** Proxy server Server connection status

Select edition you want to enable on the next launch.
Set URL for License server to get the license.


☐ FULL edition
☒ RUN edition
☐ Managed RUN edition
☐ Use the same URL as the one for Management server

License server 1 Example: https://192.0.2.0/
 URL **Check connection**
 Password
 Client certificate ...
 Certificate password

Table 5-1. Result dialog of checking license server connection

No.	Connection status	Result dialog
1	Connected to the license server, and the license can be obtained	
2	Not connected to the license server	


5. To switch the license ("FULL edition," "RUN edition," or "Managed RUN edition"), check the license you want to use.




If switching is restricted by the license server administrator, the buttons to select the license cannot be checked.

6. After completing the settings, click the 'OK' button.
The confirmation window appears.

7. Click the 'OK' button to change the settings.




8. Click the 'OK' button.



9. Restart WinActor to apply the license server connection settings.

After the restart, "Running under Product license." or "Running under Evaluation license." is displayed on the 'About WinActor' dialog.




6. [AL] AI integration license server connection settings

This chapter describes the steps for configuring the AI integration license server connection settings.

Steps

1. Click 'Tool' > 'Option' on the menu bar.



The 'Option' dialog appears.


2. On the 'AI integration license server' tab, fill 'Support ID' and 'Password,' and enter any name for 'PC name.'

The screenshot shows a software window titled 'Option' with a close button (X) in the top right corner. Below the title bar is a menu bar with the following items: Record, Edit, Date and time, Log, Screen saver, Update, Browser, Guidance, Misc., Management server, AI integration license server (which is highlighted), Proxy server, Server connection status, Log server, and Run. The main content area contains the following text: 'Please set your 'Support ID' and 'Password' for license acquisition. You can enter in the 'PC name' field a name to identify your environment. Click the 'Refresh' button to update the status of AI usage and license usage.' Below this text is a section titled 'AI integration license server' enclosed in a blue border. This section contains three input fields: 'Support ID' with the text 'XXXXXXXXXX', 'Password' with ten black dots, and 'PC name' with the text 'TEST'. To the right of the 'Support ID' field is a 'Check authentication' button, and to the right of the 'PC name' field is a 'Refresh' button. Below the 'AI integration license server' section, the text 'Last updated :' is displayed. Further down, there is a section for 'Generative AI usage' showing 'Consumption rate : ---%' and '(Total : --- / Limit : ---)'. Below this, another 'Last updated :' label is present. The next section shows 'Support ID ---', 'License type' with two radio buttons labeled 'FULL edition' and 'RUN edition', 'Number of licenses Active : --- / Total : ---', and 'Termination date and time of the support period ---'. At the bottom of this section are two rectangular boxes labeled 'Last updated' and 'PC name'. At the very bottom of the window are 'OK' and 'Cancel' buttons.



- Ask your agency for the information required to connect to the AI integration license server.

3. Configure settings on the 'Proxy server' tab when you use a proxy server.



Option

Server connection status Log server Run Record Edit Date and time
Log Screen saver Update Browser Guidance Misc.
Management server AI integration license server Proxy server

☒ Use proxy server

Select how to configure proxy server.

☐ Use your computer's proxy settings

☐ Use OS (WinHTTP) settings

☐ Use setup script(pac)

Script address

☐ Set manually

Address 192.168.0.1

Port 2301

☒ Authentication required

Authentication method Basic/Digest authentication

Username winactor

Password

Domain

OK Cancel



- A proxy server with authentications is also supported. Basic authentication, digest authentication, and NTLM authentication are supported.

4. You can check the status of the connection to the AI integration license server and the authentication of the AI integration license by clicking the 'Check authentication' button.

Option

Record Edit Date and time Log Screen saver Update Browser Guidance Misc.
Management server **AI integration license server** Proxy server Server connection status Log server Run

Please set your 'Support ID' and 'Password' for license acquisition.
You can enter in the 'PC name' field a name to identify your environment.
Click the 'Refresh' button to update the status of AI usage and license usage.

AI integration license server

Support ID XXXXXXXXXX **Check authentication**

Password ●●●●●●●●

PC name TEST Refresh

Table 6-1. Result dialog of checking authentication on the AI integration license server


No.	Connection status	Result dialog
1	The connection to the AI integration license server and the authentication of the AI integration license are successful. Thus, the license can be effective.	
2	The AI integration license authentication is failed.	




If the authentication failed, following the dialog message may lead you to solve the problem.

- 5.** After completing the settings, click the 'OK' button.
The confirmation dialog appears.

- 6.** Click the 'OK' button to change the settings.




- 7.** Click the 'OK' button.



WinActor will be restarted to apply AI integration license server settings.

- 8.** The 'About WinActor' dialog of the restarted WinActor displays either "Running under Product license" or "Running under Evaluation license."



7. Setting the management server connection information


This chapter describes the steps for setting the management server when using the WinActor management function.



The information required to connect to the management server depends on the environment in which you use WinActor. Ask the administrator of the management server for the required information.

Steps

1. Click 'Tool' > 'Option' on the menu bar.



The 'Option' dialog appears.

2. On the 'Management server' tab, enter 'URL' and 'Password' for Management server 1.

If a client certificate is required to connect to the management server, enter 'Client certificate' and 'Certificate password.'

If the management server has a redundant configuration, enter Management server 2 as well.

The screenshot shows a dialog box titled 'Option' with a close button (X) in the top right corner. It features several tabs: 'Log server', 'Run', 'Date and time', 'Log', and 'Misc.'. The 'Run' tab is selected, and within it, the 'Management server' sub-tab is active. Below the tabs, there is a checkbox labeled 'Operated by Management server'. The main area is divided into two sections for 'Management server 1' and 'Management server 2'. Each section contains fields for 'URL', 'Password', 'Client certificate' (with a browse button), and 'Certificate password'. A 'Check connection' button is next to the URL field in each section. A 'Clear' button is located below the second server section. At the bottom of the dialog are 'OK' and 'Cancel' buttons. A blue rectangular box highlights the input fields for both Management server 1 and Management server 2.

Option

Log server Run Date and time Log Misc.
Management server License server Proxy server Server connection status

☐ Operated by Management server

Management server 1 Example: https://192.0.2.0/
URL https://192.168.0.1/ Check connection
Password
Client certificate
Certificate password


Management server 2
URL Check connection
Password
Client certificate
Certificate password

Clear


* When "Operated by Management server" is checked, the fields of Management server 1 are mandatory. Management server 2 is a fallback of Management server 1 and its fields are optional.
* Client certificate and Certificate password are required when connecting to the server that requests client certificate.

OK Cancel

3. To be operated by the management server, check the box of "Operated by Management server."



If you check "Operated by Management server" and restart WinActor, the toolbar icons become disabled as shown in the figure below, and you will not be able to edit or run a scenario.



4. You can check the connection status with the management server by clicking the 'Check connection' button.






Table 7-1. Result dialog of checking management server connection

No.	Connection status	Result dialog
1	Connected to the management server	
2	Not connected to the management server	


5. After completing the settings, click the 'OK' button.

The confirmation window appears.

6. Click the 'OK' button to change the settings.



7. Click the 'OK' button.




8. Restart WinActor to apply the management server connection settings.

8. Checking the server connection status

This chapter describes the steps for checking the connection status of the management server and the license server.

Steps


1. Click 'Tool' > 'Option' on the menu bar.




The 'Option' dialog appears.

2. The connection status with each server is displayed on the 'Server connection status' tab.


To display the latest connection status, click the 'Refresh' button.



On the AI integration license version, the connection status of the AI integration license server is displayed in place of the license servers 1 and 2..



In the node-locked license version, only the connection status of the management server is displayed.



See the table below for the connection status.

Table 8-1. Server connection status

Connection status	Description
Connected	Displayed when it is currently communicating with the server.
Connection failed	Displayed when the connection has failed.
Unconnected	• Displayed when the connection is in progress. • Displayed on Server 2 when it is connected to Server 1 and not necessary to connect to Server 2 that has been configured.
Unconfigured	Displayed when the information required for connection is not configured.



WinActor[®] WinActor Installation Manual

NTT ADVANCED TECHNOLOGY CORPORATION

Copyright © 2013-2026 NTT, Inc. & NTT ADVANCED TECHNOLOGY CORPORATION

This document is protected under copyright law. It is forbidden to duplicate or copy any part or all of this document without prior consent. The contents of this document are subject to change without notice.

WA7-I-20260630